


KUDOS更改伴うSolidworksのライセンスサーバのIP変更について

SolidworksのライセンスサーバのIPが変更になります。お手数ですが、HOSTSファイル記載のIPアドレスの設定を変更願います

【変更手順】

- ①メモ帳でファイルパスのhostsを選択し開いてください（管理者権限で更新してください）
- ②【163.51.65.21ls-solid002】と記載している箇所のIPを『163.51.27.100』に変更してください
 - ファイルパス：C:¥Windows¥System32¥drivers¥etc

```
hosts
ファイル 編集 表示
# Copyright (c) 1993-2009 Microsoft Corp.
#
# This is a sample HOSTS file used by Microsoft TCP/IP for Windows.
#
# This file contains the mappings of IP addresses to host names. Each
# entry should be kept on an individual line. The IP address should
# be placed in the first column followed by the corresponding host name.
# The IP address and the host name should be separated by at least one
# space.
#
# Additionally, comments (such as these) may be inserted on individual
# lines or following the machine name denoted by a '#' symbol.
#
# For example:
#
#       102.54.94.97    rhino.acme.com    # source server
#       38.25.63.10   x.acme.com        # x client host
#
# localhost name resolution is handled within DNS itself.
#
#       127.0.0.1     localhost
#       ::1           localhost
#       163.51.65.21  ls-solid
```



```
hosts
ファイル 編集 表示
# Copyright (c) 1993-2009 Microsoft Corp.
#
# This is a sample HOSTS file used by Microsoft TCP/IP for Windows.
#
# This file contains the mappings of IP addresses to host names. Each
# entry should be kept on an individual line. The IP address should
# be placed in the first column followed by the corresponding host name.
# The IP address and the host name should be separated by at least one
# space.
#
# Additionally, comments (such as these) may be inserted on individual
# lines or following the machine name denoted by a '#' symbol.
#
# For example:
#
#       102.54.94.97    rhino.acme.com    # source server
#       38.25.63.10   x.acme.com        # x client host
#
# localhost name resolution is handled within DNS itself.
#
#       127.0.0.1     localhost
#       ::1           localhost
#       163.51.27.100  ls-solid002
```